

... Configuration... Ports & Pins

Port Setup and Axis Selection | Motor Outputs | Input Signals | Output Signals | Encoder/MPG's | Spindle Setup | Mill Options

Signal	Enabled	Port #	Pin Number	Active Low	Emulated	HotKey
X ++		1	0			0
X --		1	0			0
X Home		1	10			0
Y ++		1	0			0
Y --		1	0			0
Y Home		1	0			0
Z ++		1	0			0
Z --		1	0			0
Z Home		1	0			0

Pins 10-13 and 15 are inputs. Only these 5 pin numbers may be used on this screen

Automated Setup of Inputs

OK

Cancel

Apply

CV Mode

Remember

Return

On/Off

Elapsed

00:00

Z Inhibit

+0.000

Jog ON/OFF Ctrl-Alt-J

Units/Min

Units/Rev

Profile: M